

Dust Networks

Eterna™ Serial Programmer Guide



Table of Contents

About This Guide	3
Audience	3
Related Documents.....	3
Conventions and Terminology	3
Revision History	3
1 Getting Started	4
Installation	4
Setup	4
Invoke	8
2 Usage	9
Loading a Fuse Table / BSP binary file	9
Loading a software image	9
Basic Commands	10
Help	10
Erase.....	10
Read (unlocked device)	10
Read (locked device).....	10
Program with Verify	11
Verify	11
Unlock (persistent)	11
Manufacturing Support	13
Location ID.....	13
Creating an image for manufacture	13

About This Guide

This document describes the use of the Eterna Serial Programmer and the Eterna Serial Programming application.

Audience

This document is intended for system developers, hardware designers, and software developers.

Related Documents

The following related documents are available:

040-0102 Eterna Integration Guide

040-0109 Eterna Board Specific Parameter Configuration Guide

Conventions and Terminology

This guide uses the following text conventions:

- `Computer` type indicates information that you enter, such as a URL.
- **Bold type** indicates buttons, fields, and menu commands.
- *Italic type* is used to introduce a new term.
- **Note:** Notes provide more detailed information about concepts.
- **Caution:** Cautions advise about actions that might result in loss of data.
- **Warning:** Warnings advise about actions that might cause physical harm to the hardware or your person.

Revision History

Revision	Date	Description
040-0110 rev 1	2/9/2012	Initial Release
040-0110 rev 2	7/18/2012	Added examples, and clarification

1 Getting Started

Installation

ESP software is distributed as a .zip archive and doesn't require installation. To install, unarchive all files into a directory (e.g. c:\esp). ESP software calls FTDI, <http://www.ftdichip.com/>, drivers that are required for operation. The FTDI drivers can be found at <http://www.ftdichip.com/Drivers/D2XX.htm> and are referred to by FTDI as "D2XX Drivers". ESP software has been tested against D2XX Drivers revision 2.08.14.

The utility should be executed from the directory where you placed the files.

Setup


The Eterna Serial Programming solution is comprised of the Windows ESP.exe application, which in turn use the drivers supported by Future Technology Devices International (FTDI) to interface to the Eterna Serial Programmer via USB. Pairing of USB hardware to drivers is most easily accomplished in most systems by connecting the hardware and following the windows driver installation instructions.

FTDI hardware solutions are very common and as such there is a reasonable chance that the required drivers have already been installed in a system. It should also be noted as the drivers are generic to many solutions, for some of the ESP commands manual notation of the Eterna Serial Programmer's target COM ports is required.

Note that the pairing of the FTDI hardware is done to a specific USB port on a system. Changing of the USB port used to pair the Eterna Serial Programmer to the FTDI driver will result in having to reinstall the driver and additional manual notation of the Eterna Serial Programmer's target COM ports.

To pair the Eterna Serial Programmer to the FTDI driver on a system:

- 1) When the installation and mapping of the USB ports is complete, open the Device Eterna Serial Programmer to find out the COM port numbers that have been assigned to the virtual serial ports. The third COM port number listed will be the COM port used by the ESP application for communications with the Eterna Serial Programmer.
 - a. From the Start menu select **Settings -> Control Panel - System**.
 - b. Click the **Hardware** tab and then click on **Device Manager**.
 - c. Open **Ports (COM & LPT)** and note the COM ports – later you will want to identify the new COM ports that are added after the device drivers have been installed.



- 2) Connect the USB cable between the Eterna Serial Programmer and the system.

If four new COM ports appear in the device manager, go to step 7.

If the Found New Hardware Wizard appears, go to step 2.

If the Found New Hardware Wizard does not appear, do the following:


- a. Ensure that the port is functional, and that the device is connected correctly. If the Wizard still does not appear, open the Windows Device Eterna Serial Programmer to see how Windows has recognized the device.
- b. If a new “Question Mark Icon” appears , right-click the device and select Update Driver. This displays the Found New Hardware Wizard.



- c. Go to step 2.
- 3) In the Wizard, click the option to “Install from a list or specific location,” and click Next.



- 4) Select the box to “Include this location in the search.” Then, use the Browse button to navigate to the directory where ESP and the associated drivers have been stored , and click Next.



- 5) After the Wizard installs the software, click **Finish**.
- 6) When the Found New Hardware Wizard reappears, repeat steps 2 through 5 to continue the installation. Repeat these steps each time the Wizard appears.

Because of the way Windows works, you may be prompted to go through the Wizard up to eight times to complete the installation and mapping of the USB port. The Eterna Serial Programmer will install a total of four virtual serial ports, along with the USB drivers to control them.




- 7) When the installation and mapping of the USB ports is complete, open the Device Eterna Serial Programmer to find out the COM port numbers that have been assigned to

the virtual serial ports. The third COM port number listed will be the COM port used by the ESP application for communications with the Eterna Serial Programmer.


- a. Make a note of the third COM port identifier.

For example, if the new ports are COM3, COM4, COM5, and COM6, the PORT parameter used in some ESP commands will be “5”, corresponding to serial port COM5.



- 8) Configure the following Advanced Settings for each of the four new COM ports:

- a. **Right-click** on a COM port and click **Properties**.
- b. Click the **Port Settings** tab, and then click **Advanced**.
- c. Deselect the **Serial Enumerator** option, and click **OK**.
- d. Click **OK** to return to the Device Manager.
- e. Repeat this step for each of the four new COM ports. When you are finished, close the Device Manager.



Invoke

Commands are issued via a windows Command Prompt – see the Usage section for a list of commands.

2 Usage

Loading a Fuse Table / BSP binary file

Hardware configuration of IO and setting of Board Specific Parameters is accomplished with the FuseTable application, see *040-0109 Eterna Board Specific Parameter Configuration Guide*. The FuseTable application will generate a 2 KB binary file as its output. To load this file the use the program with verify with an offset of 0.

Loading a software image

Eterna Network stack software can be downloaded from www.linear.com. To load the software image use the program with verify with an offset of 800.

Basic Commands

Help

For a complete list of all the ESP options, enter:

```
C:\...\ESP\ESP
```

Erase

To erase the entire 512 KB of flash, enter:

```
C:\...\ESP\ESP -E
```

To erase a select number of pages of flash, enter:

```
C:\...\ESP\ESP -e OFFSET PAGES
```

Where OFFSET is in hexadecimal with no leading 0x and must be in multiples of 800 hexidecmial (2 KB). For example, to erase the 3rd and 4th pages enter:

```
C:\...\ESP\ESP -e 1800 2
```

Read (unlocked device)

To read the entire 512 KB of flash and store the image in a file, enter:

```
C:\...\ESP\ESP -r FILENAME
```

To read the entire a subet of flash and store the image in a file, enter:

```
C:\...\ESP\ESP -R FILENAME OFFSET BYTES
```

Where OFFSET and BYTES are in hexadecimal with no leading 0x and bytes.

For example, to read the 3rd and 4th pages enter:

```
C:\...\ESP\ESP -R third_and_fourth_pages.bin 1800 1000
```

Read (locked device)

Via the Hardware Lock Key, see *040-0109 Eterna Board Specific Parameter Configuration Guide* for details, a device can be locked to prevent access to all internal memory including the flash. To read a locked device enter:

```
C:\...\ESP\ESP -r FILENAME -u KKKKKKKK PORT
```

Where KKKKKKKK is the Hardware Lock Key, in hexadecimal, with no leading 0x. Where PORT is the COM port number identified in step 7 of the Setup section of this document. This will store the entire 512 KB in FILENAME. This will not modify the locked state of the device.

Where OFFSET is in hexadecimal with no leading 0x and must be in multiples of 800 hexadecimal (2 KB). The device will only program the number of bytes from the starting OFFSET to OFFSET + size(FILENAME).

For example, to read a device locked with a key of 0x1F2E3D4C using com port COM5 enter:

```
C:\...\ESP\ESP -r whole_image.bin -u 1F2E3D4C 5
```

Program with Verify

The program command will not erase the target memory range prior to programming. When programming a part that already contains an image, the target memory must be erased prior to programming.

To program an image enter:

```
C:\...\ESP\ESP -P FILENAME OFFSET
```

Where OFFSET is in hexadecimal with no leading 0x and must be in multiples of 800 hexadecimal (2 KB). The device will only program the number of bytes from the starting OFFSET to OFFSET + size(FILENAME). If the verify passes ESP will report on a new line:

```
Verify: PASS
```

If the verify fails ESP will report on a new line:

```
Verify: FAIL
```

Followed by a line indicating which address failed, the expected value and the value read from the failing location.

For example, to program a fuse table image onto a part:

```
C:\...\ESP\ESP -P fusetable.bin 0
```

Verify

To verify an image enter:

```
C:\...\ESP\ESP -V FILENAME OFFSET
```

Where OFFSET is in hexadecimal with no leading 0x and must be in multiples of 800 hexadecimal (2 KB). The device will only verify the number of bytes from the starting OFFSET to OFFSET + size(FILENAME). If verify fails it will report the first difference. If the verify passes ESP will report:

```
Verify: PASS
```

If the verify fails ESP will report on a new line:

```
Verify: FAIL
```

Followed by a line indicating which address failed, the expected value and the value read from the failing location.

Unlock (persistent)

Via the Hardware Lock Key, see *040-0109 Eterna Board Specific Parameter Configuration Guide* for details, a device can be locked to prevent access to all internal memory including the flash. **This command will alter part of the first page in flash, blanking the lock key in the process.** To unlock a locked device enter:

```
C:\...\ESP\ESP -u KKKKKKKK PORT
```

Where KKKKKKKK is the Hardware Lock Key and PORT is the COM port number identified in step 7 of the Setup section of this document.

Manufacturing Support

Multiple ESPs can be enabled to run in parallel on a single PC. To accomplish this the ESP software must be provided with the specific location ID and serial port for the. The serial port can be identified via the PC's "Device Manager" as described in the Setup section of this document. To determine the location ID see below.

Location ID

To determine the Location ID for a specific programmer enter the following prior to connecting the ESP:

```
C:\...\ESP\ESP -L
```

A list similar to the following will be presented:

```
locID[0] = 0x2121, devString = Eterna Serial Programmer A  
locID[1] = 0x2122, devString = Eterna Serial Programmer B
```

Use the B port's location ID with the `-i` option with any of the commands to direct the command to a specific ESP. For example to program with verify to the ESP device identified above one, enter:

```
C:\...\ESP\ESP -i 2122 -P FILENAME OFFSET
```

Creating an image for manufacture

Eterna's flash image is a combination of

- 1) a software image with it's own non-volatile image that can be modified when setting parameters such as join key and network ID.
- 2) A binary configuration file for IO and Board Specific Parameters

To create a single image for manufacturing:

- 1) Erase the contents of Eterna's flash
- 2) Load the configuration file for IO and Board Specific Parameters
- 3) Load the software image
- 4) Configure any parameters via Eterna's API to the values needed for manufacture
- 5) Read Eterna's flash contents to a 512 KB file

The binary image created from reading the flash contents now represents a single image that can be loaded using the program with verify command with an offset of zero.

Trademarks

Eterna is a trademark of Dust Networks, Inc. The Dust Networks logo, Dust, Dust Networks, and SmartMesh are registered trademarks of Dust Networks, Inc. All third-party brand and product names are the trademarks of their respective owners and are used solely for informational purposes.

Copyright

This documentation is protected by United States and international copyright and other intellectual and industrial property laws. It is solely owned by Dust Networks, Inc. and its licensors and is distributed under a restrictive license. This product, or any portion thereof, may not be used, copied, modified, reverse assembled, reverse compiled, reverse engineered, distributed, or redistributed in any form by any means without the prior written authorization of Dust Networks, Inc.

RESTRICTED RIGHTS: Use, duplication, or disclosure by the U.S. Government is subject to restrictions of FAR 52.227-14(g) (2)(6/87) and FAR 52.227-19(6/87), or DFAR 252.227-7015 (b)(6/95) and DFAR 227.7202-3(a), and any and all similar and successor legislation and regulation.

Disclaimer

This documentation is provided “as is” without warranty of any kind, either expressed or implied, including but not limited to, the implied warranties of merchantability or fitness for a particular purpose.

This documentation might include technical inaccuracies or other errors. Corrections and improvements might be incorporated in new versions of the documentation.

Dust Networks does not assume any liability arising out of the application or use of any products or services and specifically disclaims any and all liability, including without limitation consequential or incidental damages.

Dust Networks products are not designed for use in life support appliances, devices, or other systems where malfunction can reasonably be expected to result in significant personal injury to the user, or as a critical component in any life support device or system whose failure to perform can be reasonably expected to cause the failure of the life support device or system, or to affect its safety or effectiveness. Dust Networks customers using or selling these products for use in such applications do so at their own risk and agree to fully indemnify and hold Dust Networks and its officers, employees, subsidiaries, affiliates, and distributors harmless against all claims, costs, damages, and expenses, and reasonable attorney fees arising out of, directly or indirectly, any claim of personal injury or death associated with such unintended or unauthorized use, even if such claim alleges that Dust Networks was negligent regarding the design or manufacture of its products.

Dust Networks reserves the right to make corrections, modifications, enhancements, improvements, and other changes to its products or services at any time and to discontinue any product or service without notice. Customers should obtain the latest relevant information before placing orders and should verify that such information is current and complete. All products are sold subject to Dust Network's terms and conditions of sale supplied at the time of order acknowledgment or sale.

Dust Networks does not warrant or represent that any license, either express or implied, is granted under any Dust Networks patent right, copyright, mask work right, or other Dust Networks intellectual property right relating to any combination, machine, or process in which Dust Networks products or services are used. Information published by Dust Networks regarding third-party products or services does not constitute a license from Dust Networks to use such products or services or a warranty or endorsement thereof. Use of such information may require a license from a third party under the patents or other intellectual property of the third party, or a license from Dust Networks under the patents or other intellectual property of Dust Networks.

Dust Networks, Inc is a wholly owned subsidiary of Linear Technology Corporation.

© Dust Networks, Inc. 2012. All Rights Reserved.

Document Number: 040-0110 Eterna Serial Programmer Guide

Last Revised: July 18, 2012

Document Status	Product Status	Definition
Advanced Information	Planned or under development	This document contains the design specifications for product development. Dust Networks reserves the right to change specifications in any manner without notice.
Preliminary	Engineering samples and pre-production prototypes	This document contains preliminary data; supplementary data will be published at a later date. Dust Networks reserves the right to make changes at any time without notice in order to improve design and supply the best possible product. The product is not fully qualified at this point.
No identification noted	Full Production	This document contains the final specifications. Dust Networks reserves the right to make changes at any time without notice in order to improve design and supply the best possible product.
Obsolete	Not in production	This document contains specifications for a product that has been discontinued by Dust Networks. The document is printed for reference information only.

